

MIDI検定2級2次練習曲 No.2

♩ = 116

2

Synth Lead *ff* P.B.= -4096 → 0

Vibraphone *mf* < *ff*

Acoustic Piano *mf*

Electric Bass *f*

Drums

Note No.55 Vel.=70

Note No.49 Vel.=70

Note No.36 Vel.=100

Note No.38 Vel.=100

Note No.42 Vel.=48

Note No.41 Vel.=80

5

Syn.Ld. P.B.= -8192 → 0

Vibe *f*

Ac. Pf

E.Bass

Dr.

Note No.46 Vel.=48

Note No.45 Vel.=80

MIDI検定2級2次練習曲 No. 2

8

Syn.Ld. P.B.= -8192 → 0

Vibe

Ac. Pf

E.Bass

Dr.

11

Syn.Ld. P.B.= -8192 → 0 P.B.= -8192 → 0

Vibe *ff*

Ac. Pf *f*

E.Bass *ff*

Dr.

Note No.55
Vel.=70

Note No.49
Vel.=70

Note No.55
Vel.=70

Note No.48
Vel.=80

Note No.49
Vel.=70

Note No.55
Vel.=70

MIDI検定2級2次練習曲 No.2 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1~128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PG	83		PG	12		PG	1		PG	34	
1	2	030	CC	#7	120	CC	#7	90	CC	#7	96	CC	#7	108
1	2	040	CC	#10	64	CC	#10	32	CC	#10	80	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	60	CC	#91	64	CC	#91	70	CC	#91	20
1	2	070	CC	#93	20	CC	#93	42	CC	#93	32	CC	#93	0

			10CH		
1	2	000	CC	#0	120
1	2	010	CC	#32	0
1	2	020	PG	1	
1	2	030	CC	#7	112
1	2	040	CC	#10	64
1	2	050	CC	#11	127
1	2	060	CC	#91	50
1	2	070	CC	#93	0

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。