

令和元年度MIDI検定2級2次試験練習曲 No.3

2 $\text{♩} = 153$

Strings Melo

Strings 1st

Strings 2nd

Strings 3rd

Strings Lo

Glockenspiel

Timpani

Bass

Drums

Wood Block Hi
Wood Block Lo
Cabasa

St. Melo

St 1st

St 2nd

St 3rd

St Lo

Glk.

Timpani

Bass

Dr

W. Bl.
W. Bl.
Cab.

ff

ff

ff

ff

ff

ff

mf < ff

mf < ff

mf < ff

mf < ff

mf <

f

Note No.59 Vel.=112

Note No.38 Vel.=48

Note No.76 Vel.=80

Note No.77 Vel.=80

f

f

f

f

f

mf < ff

mf < ff

Note No.36 Vel.=100

Note No.69 Vel.=80

2020/1/15

10 C.C.#11 = 127 → 70 127 11 > 12

St. Melo *f*

St 1st *ff*

St 2nd *ff*

St 3rd *ff*

St Lo *ff*

Glk.

Timpani *mf* < *ff* *mf* < *ff* *mf* <

Bass

Dr

W. Bl.
W. Bl.
Cab.

13 > 14 >

St. Melo

St 1st

St 2nd

St 3rd

St Lo

Glk.

Timpani *ff* *mf* < *ff*

Bass

Dr

W. Bl.
W. Bl.
Cab.

令和元年度MIDI 検定2級2次練習曲 No.3 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1～128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PC	49		PC	49		PC	49		PC	49	
1	2	030	CC	#7	125	CC	#7	100	CC	#7	106	CC	#7	116
1	2	040	CC	#10	64	CC	#10	20	CC	#10	57	CC	#10	92
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	120	CC	#91	100	CC	#91	96	CC	#91	93
1	2	070	CC	#93	0	CC	#93	0	CC	#93	0	CC	#93	0

			5CH			6CH			7CH			8CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PC	49		PC	10		PC	48		PC	34	
1	2	030	CC	#7	121	CC	#7	100	CC	#7	100	CC	#7	100
1	2	040	CC	#10	100	CC	#10	43	CC	#10	40	CC	#10	70
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	92	CC	#91	70	CC	#91	100	CC	#91	20
1	2	070	CC	#93	0	CC	#93	0	CC	#93	0	CC	#93	0

			10CH		
1	2	000	CC	#0	120
1	2	010	CC	#32	0
1	2	020	PC	49	
1	2	030	CC	#7	100
1	2	040	CC	#10	64
1	2	050	CC	#11	127
1	2	060	CC	#91	80
1	2	070	CC	#93	0

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。