

令和6年度MIDI検定2級2次試験練習曲 No.1

♩=120

2 G7

Electric Organ *ff*

Electric Guitar (Mute) *mf*

Acoustic Piano *f*

Electric Bass *ff*

Drums

Note No.36 Vel.= 100

Note No.38 Vel.= 100

Note No.42 Vel.= 48

Note No.46 Vel.= 80

Note No.49 Vel.= 80

gvb

6 C7

E.Organ C.C.#11= 127 → 80 → 127

E.Guit.

Ac.Pf

E.Bass

Dr.

Note No.44 Vel.= 80

Note No.45 Vel.= 96

Note No.51 Vel.= 80

令和6年度MIDI検定2級2次試験練習曲 No. 1

8 Bm7 E7 Am7 D7 Ab7

E.Organ

E.Guit.

Ac.Pf

E.Bass

Dr.

gub

Note No.46
Vel.= 96

Note No.52
Vel.= 80

Note No.57
Vel.= 80

Note No.41
Vel.= 96

11 G7 F#7 F7 Eb7 G7

E.Organ

E.Guit.

Ac.Pf

E.Bass

Dr.

C.C.#11= 127 → 48 → 127

Note No.49
Vel.= 80

Note No.46
Vel.= 80

Note No.48
Vel.= 80

Note No.45
Vel.= 80

Note No.41
Vel.= 80

令和6年度MIDI 検定2級2次練習曲 No.1 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1～128で記載されています。

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PG	19		PG	29		PG	1		PG	34	
1	2	030	CC	#7	110	CC	#7	80	CC	#7	90	CC	#7	104
1	2	040	CC	#10	64	CC	#10	32	CC	#10	80	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	58	CC	#91	42	CC	#91	52	CC	#91	46
1	2	070	CC	#93	0	CC	#93	0	CC	#93	24	CC	#93	0

			10CH		
1	2	000	CC	#0	120
1	2	010	CC	#32	0
1	2	020	PG	1	
1	2	030	CC	#7	108
1	2	040	CC	#10	64
1	2	050	CC	#11	127
1	2	060	CC	#91	48
1	2	070	CC	#93	0

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。

※セットアップは、tpqn = 480で設定されています。