

MIDI Lisence G2 2014 No.4

♩=110

B♭m7

2

Flute

Brass Section

Synth Brass

Clavinet

Electric Bass

Drums

ff

f

mf

ff

C.C.#11 =127 → 80 → 127

Note No.36
Vel.= 112

Note No.38
Vel.= 112

Note No.46
Vel.= 80

Note No.42
Vel.= 48

5

E♭7

D♭M7

Fl.

Brass Sec.

Syn.Brass

Clavi

E.Bass

Dr.

C.C.#11 =127 → 80 → 127

P.B.= 1365 0

P.B.= 1365 0

Note No.47
Vel.= 96

8 C7(b9) F7 D^bM7 Gm7 C

Fl. C.C.#1 = 24 → 42 0 C.C.#1 = 16 → 48 0

Brass Sec. *fp* C.C.#11 = 127 → 80 → 127 C.C.#11 = 127 → 70 → 127 C.C.#11 = 127 → 62 → 127

Syn.Brass C.C.#11 = 127 → 80 → 127

Note No.49 Vel.= 80 Note No.41 Vel.= 80 Note No.44 Vel.= 32 Note No.43 Vel.= 96

11 B^bm7

Fl.

Brass Sec.

Syn.Brass

Clavi

E.Bass

Dr.

MIDI License 2014 No. 4 セットアップデータ

システムエクスクルーシブ

| | | | | | | | | |
|---|---|-----|----|----|----|----|----|----|
| 1 | 1 | 000 | F0 | 7E | 7F | 09 | 03 | F7 |
|---|---|-----|----|----|----|----|----|----|

各チャンネルのセットアップデータ

※プログラムチェンジは1~128で記載されています

| | | | 1CH | | | 2CH | | | 3CH | | | 4CH | | |
|---|---|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|
| 1 | 2 | 000 | CC | #0 | 121 | CC | #0 | 121 | CC | #0 | 121 | CC | #0 | 121 |
| 1 | 2 | 010 | CC | #32 | 0 | CC | #32 | 0 | CC | #32 | 0 | CC | #32 | 0 |
| 1 | 2 | 020 | PG | 74 | | PG | 62 | | PG | 63 | | PG | 8 | |
| 1 | 2 | 030 | CC | #7 | 122 | CC | #7 | 90 | CC | #7 | 72 | CC | #7 | 96 |
| 1 | 2 | 040 | CC | #10 | 64 | CC | #10 | 48 | CC | #10 | 64 | CC | #10 | 80 |
| 1 | 2 | 050 | CC | #11 | 127 | CC | #11 | 127 | CC | #11 | 127 | CC | #11 | 127 |
| 1 | 2 | 060 | CC | #91 | 52 | CC | #91 | 52 | CC | #91 | 48 | CC | #91 | 48 |
| 1 | 2 | 070 | CC | #93 | 16 | CC | #93 | 0 | CC | #93 | 48 | CC | #93 | 12 |

| | | | 5CH | | | 10CH | | |
|---|---|-----|-----|------|-----|------|-----|-----|
| 1 | 2 | 000 | CC | #0 | 121 | CC | #0 | 120 |
| 1 | 2 | 010 | CC | #32 | 0 | CC | #32 | 0 |
| 1 | 2 | 020 | PG | 37 | | PG | 1 | |
| 1 | 2 | 030 | CC | #7 | 102 | CC | #7 | 100 |
| 1 | 2 | 040 | CC | #10 | 64 | CC | #10 | 64 |
| 1 | 2 | 050 | CC | #11 | 127 | CC | #11 | 127 |
| 1 | 2 | 060 | CC | #91 | 44 | CC | #91 | 42 |
| 1 | 2 | 070 | CC | #93 | 0 | CC | #93 | 0 |
| 1 | 2 | 080 | CC | #101 | 0 | | | |
| 1 | 2 | 090 | CC | #100 | 0 | | | |
| 1 | 2 | 100 | CC | #6 | 12 | | | |
| 1 | 2 | 110 | CC | #101 | 127 | | | |
| 1 | 2 | 120 | CC | #100 | 127 | | | |

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。