

MIDI License G2 2018 No.4

Tempo: ♩ = 124

Chords: Am7 *gva*, G7, Dadd9 F#, FM7

Lyrics: 1つのノートで入力

Flute: *ff*, C.C.#1 = 28 → 68 0, P.B. = 4096 0

Brass Section: *mf*

Electric Piano: *mf*

Acoustic Bass: *f*, P.B. = 1365 0

Drums: Note No.45 Vel.=100, Note No.55 Vel.=80, Note No.40 Vel.=100

Percussions: Note No.36 Vel.=100, Note No.41 Vel.=100, Note No.44 Vel.=80, Note No.69 Vel.=64

Chords: E (*gva*), Am7, G7

Flute: C.C.#1 = 36 → 58 0, P.B. = 1365 0

Brass Section: *f*

Electric Piano: *f*

Acoustic Bass: *f*, P.B. = 1365 0

Drums: P.B. = 1365 0

Percussions: P.B. = 1365 0

Dadd9
F#
(gva)

FM7

E

FM7

9

Fl.

Brs. Sec.

E.Piano

Ac.Bass

Dr.

Perc.

C.C.#1 =28 → 72 0

Note No.45
Vel.=100

Note No.51
Vel.=80

Note No.80
Vel.=80

Note No.81
Vel.=80

E G F E Am

(gva)

12

Fl.

Brs. Sec.

E.Piano

Ac.Bass

Dr.

Perc.

C.C.#1 =36 → 80 0 L3

P.B.= 4096 0 4096 0

Note No.46
Vel.=100

Note No.44
Vel.=1

1つのノートで入力

MIDI License 2018 No. 4 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1~128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PC	74		PC	62		PC	5		PC	33	
1	2	030	CC	#7	116	CC	#7	76	CC	#7	90	CC	#7	98
1	2	040	CC	#10	64	CC	#10	48	CC	#10	64	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	44	CC	#91	46	CC	#91	52	CC	#91	40
1	2	070	CC	#93	0	CC	#93	0	CC	#93	32	CC	#93	0
1	2	080										CC	#101	0
1	2	090										CC	#100	0
1	2	100										CC	#6	12
1	2	110										CC	#101	127
1	2	120										CC	#100	127

			10CH			11CH		
1	2	000	CC	#0	120	CC	#0	120
1	2	010	CC	#32	0	CC	#32	0
1	2	020	PC	1		PC	1	
1	2	030	CC	#7	94	CC	#7	80
1	2	040	CC	#10	64	CC	#10	96
1	2	050	CC	#11	127	CC	#11	127
1	2	060	CC	#91	32	CC	#91	0
1	2	070	CC	#93	0	CC	#93	0