

# 令和4年度MIDI検定2級2次試験練習曲 No.3

♩ = 100

Fm7

Fm7  
B $\flat$

E $\flat$ M7

2

Flute

Vibraphone

E.Piano

Fretless Bass

Drums

Note No.42  
Vel.=64

Note No.36  
Vel.=100

Note No.37  
Vel.=96

P.B.= 1365 0

P.B.= 1365 0

P.B.= 1365 0

6

Fl.

Vibe

E.P.

Fretless Bass

Dr.

Gm7(b5)

C7(b13)

Fm7

C.C.#1=10 → 64 0

Fm7  
B $\flat$

Note No.46  
Vel.=64

Note No.59  
Vel.=96 (※1)

P.B.= 1365 0

P.B.= 1365 0

P.B.= 1365 0

令和4年度MIDI検定2級2次試験練習曲 No.3

Chord progression: Gm7 C, Bbm7 Eb7, AbM7 Gm7 Fm7

C.C.#1 = 18 → 54 0

P.B. = 1365 0

Chord progression: Fm7 Bb, A7 AbM7 Gm7 Fm7, Fm7 Bb, EbM7

C.C.#1 = 24 → 72 0

Fl. (Flute):

- Measures 9-11: Melodic line with a triplet in measure 10.
- Measure 12: Rest.
- Measures 13-14: Melodic line.
- Measure 15: Rest.
- Measures 16-17: Melodic line with a triplet in measure 17.

Vibe (Vibraphone):

- Measures 9-11: Melodic line.
- Measures 13-14: Melodic line.
- Measures 16-17: Melodic line with a triplet in measure 17.

E.P. (Electric Piano):

- Measures 9-11: Chordal accompaniment.
- Measures 13-14: Chordal accompaniment.
- Measures 16-17: Chordal accompaniment.

Fretless Bass:

- Measures 9-11: Melodic line.
- Measures 13-14: Melodic line.
- Measures 16-17: Melodic line.

Dr. (Drums):

- Measures 9-11: Rhythmic pattern with 'x' marks for cymbals.
- Measures 13-14: Rhythmic pattern with 'x' marks for cymbals.
- Measures 16-17: Rhythmic pattern with 'x' marks for cymbals.

Annotations:

- Note No.48 Vel.=80
- Note No.45 Vel.=80
- Note No.41 Vel.=80
- Note No.51 Vel.=96
- Note No.55 Vel.=80
- Note No.52 Vel.=80
- Note No.59 Vel.=96
- Note No.51 Vel.=96
- Note No.55 Vel.=96
- Note No.38 Vel.=80
- Note No.52 Vel.=80

令和4年度MIDI検定2級2次試験練習曲 No.3 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1~128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PC	74		PC	12		PC	5		PC	36	
1	2	030	CC	#7	90	CC	#7	112	CC	#7	90	CC	#7	112
1	2	040	CC	#10	48	CC	#10	64	CC	#10	80	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	58	CC	#91	54	CC	#91	52	CC	#91	54
1	2	070	CC	#93	0	CC	#93	24	CC	#93	40	CC	#93	0
1	2	080										CC	#101	0
1	2	090										CC	#100	0
1	2	100										CC	#6	12
1	2	110										CC	#101	127
1	2	120										CC	#100	127

			10CH		
1	2	000	CC	#0	120
1	2	010	CC	#32	0
1	2	020	PC	1	
1	2	030	CC	#7	108
1	2	040	CC	#10	64
1	2	050	CC	#11	127
1	2	060	CC	#91	48
1	2	070	CC	#93	0

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。  
 ※セットアップは、tpqn = 480で設定されています。