

令和4年度MIDI検定2級2次試験練習曲 No.4

♪ = 159

2

Clarinet

Glockenspiel

Strings

Piano

Contrabass

Tambourine

Note No.54
Vel.=80

6

Cl.

Glo.

Str.

Pno.

Cb.

Tamb.

10

Cl. Glo. Str. Pno. Cb. Tamb.

Detailed description: This block contains the first system of the musical score, covering measures 10 through 13. It features six staves: Clarinet (Cl.), Glockenspiel (Glo.), Strings (Str.), Piano (Pno.), Contrabass (Cb.), and Tambourine (Tamb.). The key signature is two flats (B-flat and E-flat). The Clarinet part has a long melodic line with slurs and a fermata. The Glockenspiel part has sparse notes. The Strings part plays a steady eighth-note accompaniment. The Piano part has a rhythmic eighth-note pattern in the right hand and a bass line in the left hand. The Contrabass part has a simple bass line. The Tambourine part has a consistent rhythmic pattern.

14

Cl. Glo. Str. Pno. Cb. Tamb.

C.C.#11 = 127 → 72

Detailed description: This block contains the second system of the musical score, covering measures 14 through 17. It features the same six staves as the first system. The key signature remains two flats. The Clarinet part continues its melodic line. The Glockenspiel part has more notes. The Strings part continues its accompaniment, with a crescendo hairpin starting in measure 16. The Piano part continues its rhythmic pattern. The Contrabass part continues its bass line. The Tambourine part continues its rhythmic pattern. A rehearsal mark 'C.C.#11 = 127 → 72' is placed above the Strings staff in measure 16.

令和4年度MIDI検定2級2次試験練習曲 No.4 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1～128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PC	72		PC	10		PC	49		PC	1	
1	2	030	CC	#7	120	CC	#7	100	CC	#7	80	CC	#7	100
1	2	040	CC	#10	64	CC	#10	71	CC	#10	40	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	58	CC	#91	61	CC	#91	60	CC	#91	40
1	2	070	CC	#93	0	CC	#93	0	CC	#93	0	CC	#93	0

			5CH			10CH		
1	2	000	CC	#0	121	CC	#0	120
1	2	010	CC	#32	0	CC	#32	0
1	2	020	PC	33		PC	1	
1	2	030	CC	#7	100	CC	#7	100
1	2	040	CC	#10	64	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127
1	2	060	CC	#91	30	CC	#91	70
1	2	070	CC	#93	0	CC	#93	0

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。
 ※セットアップは、tpqn = 480で設定されています。