

MIDI Lisence G2 2014 No.2

♩=146

2

E♭M7 Dm7 Cm7 Dm7 Gm7 Cm7 Dm7 E♭M7 Dm7

P.B.=-4096 → 0 P.B.=-4096 → 0

Synth Lead

Overdrive Guitar *ff* ※1

Synth Brass *f*

Strings *f*

Electric Bass *ff*

Drums

Note No.50 Vel.= 80
Note No.40 Vel.= 112
Note No.36 Vel.= 112
Note No.47 Vel.= 80
Note No.43 Vel.= 80
Note No.46 Vel.= 64
Note No.42 Vel.= 48
Note No.49 Vel.= 80

G7 Cm7 F7(♭9) B♭M7 E♭M7 Am7(♭5)

6

Syn Ld

Od.Gt. C.C.#1 =20 → 64 0

Syn. Brass

St.

E.Bass

Dr.

Note No.57 Vel.= 80
Note No.49 Vel.= 80
Note No.57 Vel.= 80

Am7
D
P.B.=
0 → 8191 0

9

Syn Ld

Od.Gt.

Syn. Brass

St.

E.Bass

Dr.

C.C.#11 =127 → 64 → 127

C.C.#1 =20 → 64 0

Note No.49
Vel.= 80

Cm7 Bbm7 AbM7
P.B.= -8192 → 0

12

Syn Ld

Od.Gt.

Syn. Brass

St.

E.Bass

Dr.

C.C.#1 =20 → 72 0

C.C.#11 =127 → 0

C.C.#11 =127 → 0

Note No.57
Vel.= 80

Note No.55
Vel.= 80

Note No.49
Vel.= 80

Note No.49
Vel.= 96

MIDI License 2014 No.2 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1~128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PG	82		PG	30		PG	63		PG	49	
1	2	030	CC	#7	118	CC	#7	108	CC	#7	76	CC	#7	96
1	2	040	CC	#10	64	CC	#10	32	CC	#10	64	CC	#10	96
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	56	CC	#91	58	CC	#91	52	CC	#91	52
1	2	070	CC	#93	16	CC	#93	32	CC	#93	24	CC	#93	32

			5CH			10CH		
1	2	000	CC	#0	121	CC	#0	120
1	2	010	CC	#32	0	CC	#32	0
1	2	020	PG	34		PG	17	
1	2	030	CC	#7	100	CC	#7	106
1	2	040	CC	#10	64	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127
1	2	060	CC	#91	48	CC	#91	46
1	2	070	CC	#93	0	CC	#93	0

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。