

# MIDI Lisence G2 2015 No.2

**Tempo:** ♩ = 108

**Chords:** Dm7, Em7, Am7, Gm7 C7, FM7, Em7

**Harmonica:** C.C.#1 = 12 → 60 0, C.C.#1 = 10 → 48 0

**Music Box:** P.B. = -8192 → 0

**Strings:** C.C.#11 = 127 → 80 → 127, C.C.#11 = 127 → 64

**E.Guitar:** f

**E.Piano:** f

**E.Bass:** ff, Note No.43 Vel.=80, Note No.38 Vel.=112, Note No.49 Vel.=80, Note No.46 Vel.=64, P.B. = 1365 0

**Drums:** Note No.36 Vel.=112, Note No.47 Vel.=80, Note No.42 Vel.=48

**Chords (Bottom):** Am7, Em7 A, Eb7, Dm7, Em7, Am7 Eb7, Dm7

**Harmonica (Bottom):** C.C.#1 = 14 → 62 0

**Music Box (Bottom):** P.B. = -8192 → 0

**Strings (Bottom):** mf, ff

**E.Guitar (Bottom):** P.B. = 1365 0

**E.Piano (Bottom):** P.B. = 1365 0

**E.Bass (Bottom):** P.B. = 1365 0, h.

**Drums (Bottom):** P.B. = 1365 0, h.

10

Chords: Gm7, Gm7/C, Gb7, FM7, Em7, Am7, Gm7, Gb7, FM7, Em7

Harmonica: C.C.#1 = 10 → 64 0, C.C.#1 = 8 → 48 0, P.B. = -4096 → 0, P.B. = -8192 → 0, P.B. = -4096 → 0, P.B. = 0 → -8192 0, P.B. = -8192 → 0

Music Box: -

Strings: *mf*, *ff*

E.Guitar: → 20 127, C.C.#11 = 127, → 20 127, C.C.#11 = 127 → 82

E.Piano

E.Bass

Drums: Note No.46 Vel.=80, P.B.=1365 0, Note No.49 Vel.=80, P.B.= 1365 0 1365 0

Chords: Am7, Em7/A, Eb7, Dm7

14

Harmonica: C.C.#1 = 14 → 72 0

Music Box: -

Strings: 8, 8

E.Guitar: → 127 → 20 127, C.C.#11 = 127 → 0, *ppp*

E.Piano

E.Bass

Drums: Note No.47 Vel.=96, Note No.55 Vel.=80, Note No.43 Vel.=96, Note No.49 Vel.=80, Note No.41 Vel.=96

MIDI License 2015 No.2 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1~128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PG	23		PG	11		PG	49		PG	29	
1	2	030	CC	#7	116	CC	#7	100	CC	#7	72	CC	#7	100
1	2	040	CC	#10	64	CC	#10	48	CC	#10	80	CC	#10	88
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	58	CC	#91	52	CC	#91	56	CC	#91	48
1	2	070	CC	#93	0	CC	#93	24	CC	#93	22	CC	#93	0

			5CH			6CH			10CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	120
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PG	5		PG	34		PG	1	
1	2	030	CC	#7	86	CC	#7	94	CC	#7	100
1	2	040	CC	#10	48	CC	#10	64	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	54	CC	#91	40	CC	#91	48
1	2	070	CC	#93	28	CC	#93	0	CC	#93	0
1	2	080				CC	#101	0			
1	2	090				CC	#100	0			
1	2	100				CC	#6	12			
1	2	110				CC	#101	127			
1	2	120				CC	#100	127			

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。