

MIDI License G2 2019 No.1

♩ = 160

P.B. = -1365 → 0

Bm

G

P.B. = -1365 → 0

2

Synth Lead

Musical notation for Synth Lead, measures 2-4. Includes dynamics *ff* and C.C.#1 = 17 → 50 0.

String Ensembles

Musical notation for String Ensembles, measures 2-4. Includes dynamics *ff* and C.C.#11 = 81 → 127.

Electric Piano

Musical notation for Electric Piano, measures 2-4. Includes dynamics *f*.

Electric Guitar

Musical notation for Electric Guitar, measures 2-4. Includes dynamics *f*.

Synth Bass

Musical notation for Synth Bass, measures 2-4. Includes dynamics *ff*.

Drums

Musical notation for Drums, measures 2-4. Includes specific note annotations: Note No.45 Vel.=100, Note No.41 Vel.=100, Note No.48 Vel.=100, Note No.36 Vel.=100, Note No.49 Vel.=90, Note No.46 Vel.=64, Note No.40 Vel.=100.

5

Em

F#7

Bm

D

Em

F#7

Syn.

Musical notation for Syn., measures 5-7. Includes C.C.#1 = 34 → 58 0.

Str.

Musical notation for Str., measures 5-7. Includes C.C.#11 = 127 → 50 127 and dynamics *mp* and *f*.

E.P.

Musical notation for E.P., measures 5-7.

E.G.

Musical notation for E.G., measures 5-7.

S.B.

Musical notation for S.B., measures 5-7.

Drs.

Musical notation for Drs., measures 5-7.

8

Bm G Em7 F#7 P.B.= -1365 → 0

Syn.

Str.

E.P.

E.G.

S.B.

Drs.

mp *f* *p*

11

GM7 C.C.#1 = 15 → 49 0 A P.B.= -1365 → 0 Bm C.C.#1 = 12 → 48 0

Syn.

Str.

E.P.

E.G.

S.B.

Drs.

f *p* *f* *p* *f*

ff

1つのノートで入力 1つのノートで入力

P.B.= 1365 0 P.B.= 1365 0

Note No.42
Vel.=1

MIDI License 2019 No.1 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1～128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PC	81		PC	49		PC	5		PC	30	
1	2	030	CC	#7	116	CC	#7	88	CC	#7	80	CC	#7	84
1	2	040	CC	#10	64	CC	#10	48	CC	#10	80	CC	#10	32
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	68	CC	#91	52	CC	#91	50	CC	#91	62
1	2	070	CC	#93	0	CC	#93	42	CC	#93	32	CC	#93	36
1	2	080	CC	#101	0									
1	2	090	CC	#100	0									
1	2	100	CC	#6	12									
1	2	110	CC	#101	127									
1	2	120	CC	#100	127									

			5CH			10CH		
1	2	000	CC	#0	121	CC	#0	120
1	2	010	CC	#32	0	CC	#32	0
1	2	020	PC	39		PC	1	
1	2	030	CC	#7	88	CC	#7	100
1	2	040	CC	#10	64	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127
1	2	060	CC	#91	20	CC	#91	52
1	2	070	CC	#93	0	CC	#93	0
1	2	080	CC	#101	0			
1	2	090	CC	#100	0			
1	2	100	CC	#6	12			
1	2	110	CC	#101	127			
1	2	120	CC	#100	127			

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。