

MIDI検定2級2次練習曲 No.4

2 ♩ = 121 C.C.#1 = 20 → 42 0

Synth. Lead

Sequence 1

Sequence 2

Mute Guitar

Electric Guitar

Electric Piano

Synth Bass

Drums

6

Syn.Ld.

Seq.1

Seq.2

Mute.Gt.

E.Guit.

E.Pf.

Syn.Ba.

Dr.

ff

f

f

mf

mf

ff

Note No.38 Vel.=100

Note No.41 Vel.=100

Note No.42 Vel.=100

Note No.46 Vel.=100

Note No.36 Vel.=100

一つのノートで入力

P.B.=1365 0

一つのノートで入力

P.B.=1365 0

MIDI検定2級2次練習曲 No.4

9 C.C.#1= 20 → 50 0

Syn.Ld.

Seq.1

Seq.2

Mute.Gt.

一つのノットで入力
P.B.=1365 0

E.Guit.

E.Pf.

Syn.Ba.

Dr.

12

Syn.Ld.

Seq.1

Seq.2

Mute.Gt.

E.Guit.

E.Pf.

Syn.Ba.

Dr.

MIDI検定2級2次練習曲 No.4 セットアップデータ

システムエクスクルーシブ

1	1	000	F0	7E	7F	09	03	F7
---	---	-----	----	----	----	----	----	----

各チャンネルのセットアップデータ

※プログラムチェンジは1～128で記載されています

			1CH			2CH			3CH			4CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	121
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PC	88		PC	81		PC	81		PC	29	
1	2	030	CC	#7	100	CC	#7	80	CC	#7	80	CC	#7	97
1	2	040	CC	#10	64	CC	#10	70	CC	#10	60	CC	#10	13
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	40	CC	#91	40	CC	#91	40	CC	#91	32
1	2	070	CC	#93	0	CC	#93	0	CC	#93	0	CC	#93	0
												CC	#101	0
												CC	#100	0
												CC	#6	12
												CC	#101	127
												CC	#100	127

			5CH			6CH			7CH			10CH		
1	2	000	CC	#0	121	CC	#0	121	CC	#0	121	CC	#0	120
1	2	010	CC	#32	0	CC	#32	0	CC	#32	0	CC	#32	0
1	2	020	PC	28		PC	5		PC	40		PC	26	
1	2	030	CC	#7	82	CC	#7	100	CC	#7	100	CC	#7	100
1	2	040	CC	#10	101	CC	#10	64	CC	#10	64	CC	#10	64
1	2	050	CC	#11	127	CC	#11	127	CC	#11	127	CC	#11	127
1	2	060	CC	#91	26	CC	#91	40	CC	#91	40	CC	#91	40
1	2	070	CC	#93	0	CC	#93	79	CC	#93	0	CC	#93	0

※シーケンスソフトによっては、表記と表示およびタイミングが異なる場合があります。